

Computer	Model	Key command to activate/deactivate video port
Acer	Note 350, 750, 760, 780, 950	CTRL-ALT-ESC while computer boots activates the set-up menu; system configuration; advanced system configuration; display device; LCD/CRT
	Note 971	FN+F5
AST	Ascentia, Ascentia A Series, PowerExec, 9xxN	FN+F5
	Ascentia J Series	FN+F3
	Ascentia P Series, Bravo, 800N, B5N	FN+F12
Canon	Premium Exec	FN+D
	BTO	FN+F6
	Innova 386NX	Set-up Menu Option
	Innova Book 360CD, 490CDS	FN+F7
Compaq	NoteJet 3CX	Change CMOS to CRT
	Armada, LTE, Contura	FN+F4
	Presario	FN+F2
Dell	Other	Automatic, CTRL-ALT<
	Latitude, CP-Inspiron	FN+F8 FN+F12
Epson	Other	CRTL-ALT-< FN+D
	650C	Set Switch to CRT
Fujitsu	Other	FN+F12
Gateway	Lifebook	FN+F10
	Solo, Liberty	FN+F3
	Colorbook	FN+F1
Hitachi	Colorbook 2	Option in CMOS setup
	M120T/1000, M100D	FN+F7
	E100D/810	FN+F8
Hewlett Packard	Omnibook	FN+F5
	Pavilion	FN+F12 FN+F5

IBM	Thinkpad 310, 36x, 380, 701, 75x, 760, 560, 770 Thinkpad 350, PS/Note 425C LX40 Thinkpad 700	FN+F7 FN+F1 for setup Setup LCD to CRT Ctrl+Alt+S
Macintosh	PowerBook 3400	Select Monitor Icon on PowerBook Control Strip, select resolution to match display device (e.g. 800x600 Simulscan for simultaneous display on PowerBook and on projector)
	PowerBook 1400	Requires optional video. Select Monitor Icon on PowerBook Control Strip, select resolution to match display device (e.g. 800x600 Simulscan for simultaneous display on PowerBook and on projector)
	PowerBook 1600, 165, 1800, 520, 540, 5300	Control Panel folder, PowerBook Display folder, activate Video Mirroring, warm reboot. Or (if display problem occur with mirroring) Control Panel folder, Monitor, switch primary display by dragging white menu bar to Monitor 2.
	PowerBook 140, 145, 150, 170 Portable 100	No video port. Requires 3 rd party interface. Not compatible
Micron	Millenia, Transport	FN+F2
Mitsubishi		FN+F12
	All	SW2 On Off Off Off to activate SW2 Off On On On to deactivate

NEC	Versa 2000, 4000 series, 5000 series, 6000 series, M, P, V, MX series, Ultralite	FN+F3
	Versa 2400	FN+F10
	Versa S Other	FN+F2 Select "Active" from set-up
Packard Bell	All	FN+F10
Panasonic		FN+F2
		FN+F2
	All	Panasonic set-up program
Samsung	All	FN+F4
	55200	Set-up screen option
	Pro 500	FN+F5
	Pro 800, Sens 700	FN+F6
Sanyo	All	Set-up screen option
Sharp	All	FN+F5
	6020, 6030,6050, Extensa 600CD	FN+F12
Toshiba	650CDT	FN+End
	1000, 1200, 1600,3100E, 3200	Ctrl+Alt+End
	1100	Reboot
	1850	Automatic, no simultaneous display
	T1910 Satellite, T1950CT, T1960CT	
		Type Tsetup at DOS prompt, select display location int/ext/both (internal, external, or both display)
	105CS, 110CT, 115CS, 200CDs, 400, 410, 415, 420, 430, 500CDT, 610, 650CT, 2100CT, 2105CT, 2130CS, 2150CS, 2150CDT, 2400CS, 2400CT, 2450CT, 3600DT, 4500, 4700, 4800, 4850	
		FN+F5



	4900, Tecra 700CDT, 720CDT, 730CDT	Ctrl+Alt+End
	3100	FN+End
	3100E, 3200	N/A PORT ACTIVE
	3100SX, 3200SX	Needs SCSI adapter for external video
	3400	N/A PORT ACTIVE
	4400sx	Ctrl+Alt+End
	5100	N/A PORT ACTIVE
	5100/100, 5200, 5200/100	Needs SCSI adapter for external video
Twinhead	610CT,	FN+F5
	Slimnote 5100T, 9133CX	FN+F5
	Slimnote 8xx Series	FN+F6 (simul) FN+F10 (int/ext)
Winbook	XP, XP5	FN+F12
	XP5 Pro, FX	FN+F2
	XL	FN+8